# **Samsung PC Studio 3 Installation**

This is the complete procedure for installation of Samsung PC Studio 3 software on your windows based PC (XP or 2000). Many Samsung mobiles like X700, D600, D900 etc uses this software. So, this guide works for all these mobiles.

Insert software CD into CD drive. After few seconds, a screen of "PC Studio" will appear.

PCStud SAMSUNG PC STUDI		SAMSUNG
Select Language ••••	English	Dutch
	German	Russian
	Italian	Simplified Chinese
	Spanish	Traditional Chinese
	Portuguese	Swedish
	Brazil Portuguese	Greek
	French	
		×
		SAMSUNG ELECTRONICS CO.,LTD. ALL RIGHTS RESERVED

Select the language : English



Select "Install Samsung PC Studio" option. You will see "Installshield Wizard" screen. Samsung PC Studio - InstallShield Wizard



Click "Next" button.

Samsung PC Studio - InstallShield Wizard 🛛 🛛 🗙
License Agreement Please read the following license agreement carefully.
Samsung PC Studio License Agreement
Samsung PC Studio END-USER LICENSE AGREEMENT
IMPORTANT-READ CAREFULLY: This End-User License Agreement ("EULA") is a legal agreement between you (either an individual or a single entity) and Samsung Electronics, Co., Ltd. for the Samsung Electronics SOFTWARE identified above, which includes the User Manual, any associated SOFTWARE components, any printed materials. By installing, copying, or otherwise using the SOFTWARE, you agree to be bound by the terms of this
I accept the terms of the license agreement     Print
C I do not accept the terms of the license agreement
InstallShield
<pre></pre>

Select "I accept" option and click "Next" button. Now you can see the destination location of program. Just click "Next" button.

nsung PC Studio - InstallShield Wiza	ru	
Choose Destination Location Select folder where setup will install files.		N.C.Y.
Selectrolder where setup will install files.		
Setup will install Samsung PC Studio in th	e following folder.	
To install to this folder, click Next. To inst another folder.	all to a different folder, click Browse	e and select
Destination Folder		
⊂ Destination Folder C:\Program Files\Samsung\Samsung F	PC Studio 3	Browse
C:\Program Files\Samsung\Samsung F	°C Studio 3	Browse
	°C Studio 3 ≺ Back Next >	Browse

Now, click "Install" button to begin the installation.

Samsung PC Studio - InstallShield Wizard		×
Ready to Install the Program The wizard is ready to begin installation.		No.
Click Install to begin the installation.		
If you want to review or change any of your i the wizard.	installation settings, click Back. Click	Cancel to exit
InstallShield		
	< Back Install	Cancel

#### This will start the setup process.

Samsung PC Studio - InstallShield Wizard	×
Setup Status	
Samsung PC Studio is configuring your new software installatio	ın.
Installing	
C:\Program Files\Samsung\Samsung PC Studio 3\XTP9601Li	ibL.dll
InstallShield	
	Cancel

After few seconds, you will see a message "Software Installation." Just select "Continue Anyway" option. Then you will see "InstallShield Complete" message.



After installation, exit the "PC Studio" installation window. Now, connect your Samsung

X700 mobile with PC through USB cable. After few seconds, you will see these messages on your PC :

messages on jour re.	
SAMSUNG Mobile USB Modem	
*500000/9	8:40 PM
Found New Hardware Wizard	
	Welcome to the Found New Hardware Wizard This wizard helps you install software for: SAMSUNG Mobile USB Modem 1.0 If your hardware came with an installation CD or floppy disk, insert it now. What do you want the wizard to do? Install the software automatically (Recommended)
	O Install from a list or specific location (Advanced)
	Click Next to continue.
	< Back Next > Cancel
Click "Next" button.	
Found New Hardware Wizard	
Please wait while the wize	ard searches
Samsung Mobile	USB Device 1.0
	<pre></pre>



Follow the steps of "Found New Hardware" wizard again as above. After this, you will see this message on PC:



Now, open "Samsung PC Studio" software. You will see "Not Connected" message like this:





Select "USB" then "Connect" Then press "OK" button. You will see this screen:

🔕 Connection M	anager			
Select Connection	Type: USB		Configuration	
USB	Bluetooth	Jan Infrared	Serial	
SGH-X700 Connected				
	Connec	t O	K Help	

If you are still unable to get this message, then close the software and restart your PC and again try to connect your mobile with PC.

Once you have successfully done this, you will see this message:

🔊 Samsung PC 9	Studio			
<u>F</u> ile ⊻iew <u>I</u> o	ools <u>H</u> elp			
		9	<b>%</b>	
Manage contacts and more	Manage messages	Synchronize	Manage files	Manage Internet connections
<b>U</b>		6	Co:	
Manage photos	Edit movies	Edit sounds	Compose multimedia messages	Play multimedia files
			<i>[]</i> s	GH-X700 Connected

And on taskbar, the software's icon will appear in blue / orange colour :

Samsung PC Studio « 🗳 🗊 🖏 🐼 🥢 9:

# **<u>Repairing The Software</u>**

In case, if this message appears :

😲 Found New Hardware	×
A problem occurred during hardware installation. You hardware might not work properly.	urnew
	« ZS

Then try to repair the software. Just insert CD into CD drive which will start the installation . Select language : English and select "Install Samsung PC Studio". Then you will see this screen :

Samsung PC St	udio - InstallShield Wizard			×
Maintenance	e Mode For Samsung PC Stud	dio 3.0		24
	the Samsung PC Studio Setup Mai rrent installation. Click one of the o		m. This program	lets you
Repair				
F	Reinstall all program features insta	alled by the previ	ous setup.	
C Remove				
8	Remove all installed features.			
InstallShield —				
		< Back	Next >	Cancel

Click "Next" which will reinstall the software and you will see this screen:



Do same as USB driver. After reinstalling the software and USB driver, try again to connect your mobile with PC Studio software.

### **Transfer Data through USB Mass Storage Feature**

By using "USB Mass Storage" feature of your X700 mobile, you can access your memory card from PC without using any software/driver. You just need a USB cable and X700 mobile with memory card installed.

On your mobile, select Menu/Settings/Phone Settings/USB Settings/Mass Storage select "Save" and connect your mobile to PC through USB cable. Immediately, memory card will be detected by windows and it will be installed by itself. After this, you will see this icon:



On your PC, go to "My Computer" and here you can see your memory card as a new removable drive like this:

KFAT4 (F:) K	FAT4 (F:) Properties		? X	
		ols   Hardware   Sharing	1	
	KFAT4			
	Type: Remova File system: FAT	ıble Disk		
	Used space:	477,274,112 bytes	455 MB	
	Free space:	29,655,040 bytes	28.2 MB	
	Capacity:	506,929,152 bytes	483 MB	
		Drive F		
-				
x . 1 11 11 1		OK Cancel		1011
Just double click of	n the icon of this di	Tive and you will se	e all memory ca	rd folders :
File Edit View Favorites	Tools Help			
🚱 Back 🝷 🕥 👻 🏂 🗍	🔎 Search 🛛 🌔 Folders 🛛	🏽 🖄 🗙 🍤 🛄 🕯		
Address 🗣 F:\				
Images	Music	C	Other files	Sounds
Videos				

Use Cut / Copy / Paste method to transfer all kind of files from PC to Card or Card to PC. To disconnect your memory card, there are two options:

#### **Option 1 :**

Right click on it's icon and select "Safely remove hardware" option.



Then you will see this screen :

🍫 Safely Remove Hardware	? ×
Select the device you want to unplug or eject, and ther Windows notifies you that it is safe to do so unplug the computer. Hardware devices:	
😪 USB Mass Storage Device	
USB Mass Storage Device at SAMSUNG Mobile USB Modem	
Properties	Stop
Display device components	Close
Press "Stop" button. This will appear:	
🖗 Stop a Hardware device	? ×
Confirm devices to be stopped, Choose OK to continue.	
Windows will attempt to stop the following devices. After the devicepped they may be removed safely.	vices are
Contract of the second	
ОК	Cancel

Press "OK" button.

Option 2 : Just select on your mobile : Menu/Settings/Phone Settings/USB Settings/Modem and Select "Save".

This will disconnect the memory card from PC.

©2007 usmanafzal.110mb.com All rights reserved.